



# Getting HLS:

---

## Contents

- 1 Getting HLS
  - 1.1 Download and Installation
    - 1.1.1 Download HLS
    - 1.1.2 Folder Hierarchy
    - 1.1.3 HLS Installation
    - 1.1.4 OS Specific Installation
  - 1.2 Upgrading HLS
    - 1.2.1 Standard Upgrade
    - 1.2.2 Upgrade Path for Skipped Updates

## Getting HLS

### Download and Installation

#### Download HLS

Download the software `HLS_Install_*.zip` from [1] and save it to your computer.

- One way to organize the downloaded versions is to create a folder named "HLS Versions" and save downloads there.
- Unzip the `HLS_Install_*.zip` and four files will be created in a folder named the same as the zip file. These four files are:

`DBGHELP.DLL`

`ftd2xx.dll`

`HLS.exe`

`ipworks8.dll`

#### Folder Hierarchy

Unlike a lot of software, HLS doesn't change your registry and isn't installed in a typical way. All that's necessary to get HLS up and running is to place the four files listed above into a folder and you are off and running. A little time spent on creating a foundation of folders to hold your copy of HLS will go a long way in keeping your computer organized and the files you will be creating logical and easy to find.

- At a minimum, it is suggested to create a folder layout of five folders as follows (folders needing to be created are in bold type):

HLS

HLS\**Backgrounds**

HLS\**Library**

HLS\**Music**

HLS\**Sequences**

- Each sequence you create will create additional files, therefore, it is an excellent practice to make a sub-folder under the "HLS\Sequences" folder for each new sequence you create. For example:

HLS\Sequences\**My first sequence**

#### HLS Installation

- Now that you have the foundation of folders created, copy the four files from the `HLS_Install_*.zip` version into your "HLS" folder.
- Now you are ready to run HLS.
- Note: If you are using you need to change the properties of the `HLS.exe` file to run as Administrator.
- Open `HLS.exe` and begin to sequence.

#### OS Specific Installation

Windows XP HLS Installation

Windows 7/Vista HLS Installation

Linux HLS Installation

OSX HLS Installation

### Upgrading HLS

#### Standard Upgrade

When you start up HLS, it automatically checks for the most recent version. If there is a new version, a window will open asking if you want to upgrade. If you choose yes, you will be redirected to the website to download the newest version.

- Simply download the latest version, unzip the files, and overwrite the old files with the new ones.

#### Upgrade Path for Skipped Updates

Due to the high rate of development of HLS, if a user is not monitoring the updates frequently, it is easy to fall several versions behind. If someone upgrades to the latest version from an older version, there is risk of data

loss from the sequence files no longer being able to be opened.

To address this concern, there is an upgrade path that can be taken to move from older version to the newest version. Each time an upgrade step is made, any sequences that you want to keep should be opened in that step and saved before moving to the next step.

- Upgrading from a version 11E: Install version 11H [2]
- Open any sequence you wish to keep in version 11H and
- Upgrade from to the most current version. [3]
- Open and Save sequences again to have them fully updated.

Retrieved from "[http://doityourselfchristmas.com/wiki/index.php?title=Getting\\_HLS:&oldid=10048](http://doityourselfchristmas.com/wiki/index.php?title=Getting_HLS:&oldid=10048)"

This page was last modified on 24 March 2013, at 23:37. This page has been accessed 66 times. [Privacy policy](#) [About doityourselfchristmas.com](#) [Disclaimers](#)